AD-760 549

A PROGRAMMER'S GUIDE TO PDP-10 EULER

William M. Newman, et al

Utah University

Prepared for:

Rome Air Development Center Defense Advanced Research Projects Agency

June 1970

DISTRIBUTED BY:

National Technical Information Service U. S. DEPARTMENT OF COMMERCE 5285 Port Royal Road, Springfield Va. 22151

DISCLAIMER NOTICE

THIS DOCUMENT IS THE BEST QUALITY AVAILABLE. COPY FURNISHED CONTAINED A SIGNIFICANT NUMBER OF PAGES WHICH DO NOT REPRODUCE LEGIBLY. RADC-TR- 73-152 Technical Report June 1970

AD 760549

i

1 - 1

3



A PROGRAMMER'S GUIDE TO PDP-10 EULER

University of Utah

Sponsored by Defense Advanced Research Projects Agency ARPA Order No. 829



Approved for public release; distribution unlimited.

The views and conclusions contained in this document are those of the authors and should not be interpreted as necessarily representing the official policies, either expressed or implied, of the Defense Advanced Research Projects Agency or the U. S. Government.

> Rome Air Development Center Air Force Systems Command Griffiss Air Force Base, New York

> > Reproduced by NATIONAL TECHNICAL INFORMATION SERVICE U S Department of Commerce Springfield VA 22151

UNCLASSIFIED				
Security Classification				
	CONTROL DATA -			
(Security classification of title, body of obstract and i . ORIGINATING ACTIVITY (Corporate outhor)	Indexing annotation must a		SECURITY CLASSIFICATION	
University of Utah		UNCLAS		
Salt Lake City, Utah 84112		28.		
		N/A		
SEPORT TITLE				
A PROGRAMMER'S GUIDE TO PDP-10 EULER				
A TROUMINER 5 COIDE TO THE TO EDER				
4. CISCRIPTIVE HOTES (Type of report and inclusive detee)				
S. AUTHOR(S) (First nome, middle Inilial, lest name)				
William M. Newman Henri Gouraud				
Donald R. Oestreicher				
AEPONT DATE	TA. TOTAL NO	. OF PAGES	78. NO. OF REFS	
June 1970 ·	73		3	
B. CONTRACT OR GRANT NO.	SE. ORIGINATO	SR'S REPORT NU	MOER(5)	
AF 30 (602) 4277				
ARPA Order No. 829	None			
c,	95. OTHER RE	PORT NOIS (Any	other numbers that may be easigned	
Program Code No. 6D30	this report)			
d.	RADC-TR	-73-152		
10. DISTRIBUTION STATEMENT				
Approved for public release; distrib		NG MILITARY AC	TI VI T V	
Murray Kessleman RADC (ISCE), GAFB NY 13441 AC 315 330-2018		Defense Advanced Research Projects Agency Wash DC 20301		
This manual describes the EULE computer. EULER is a block-structu simplified by omitting type declara are defined and called. PDP-10 EUL manipulation, and also for a number graphics.	ured language, s ations and by al LER includes fea	imilar to A tering the tures for 1	Algol-60 but way procedures list and array	
DD 1 NOV 45 1473		UNC		

UNCLASSIFIED					
Security Classification	LINI	C A	LINK	•	-
KEY WORDS	ROLE		ROLE		
			1 1		
Traphics					
			1 1		
Computer Graphics					
				-	
					1
		ĺ			1
		<u> </u>			
				-	
				- C	
and a second difference of the second					
i-a		UNCI	ASSIFIE	D	
1-0-			ity Classifi		

A PROGRAMMER'S GUIDE TO PDP-10 EULER

William M. Newman Henri Gouraud Donald R. Oestreicher

Contractor: University of Utah Contract Number: AF30(602)4277 Effective Date of Contract: 20 May 1966 Contract Expiration Date: 30 November 1970 Amount of Contract: \$5,028,542.00 Program Code Number: 6D30

Principal Invescigator: Thomas G. Stockham, Jr. Phone: 801 581-8224

Project Engineer: Murray Kesselman Phone: 315 330-2018

Approved for public release; distribution unlimited.

This research was supported by the Defense Advanced Research Projects Agency of the Department of Defense and was monitored by Murray Kesselman RADC (ISCE), GAFB, NY 13441 under Contract AF30(602)4277.

1-6

A PROGRAMMER'S GUIDE TO PDP-10 EULER

PUBLICATION REVIEW

This technical report has been reviewed and is approved

eaching

RADC Project Engineer MURRAY KESSELMAN

ACKNOWLEDGMENTS

EULER was originally implemented on the PDP-10 as a class exercise. Since then it has grown into a full-fledged compilerinterpreter system. We would like, however, to acknowledge the work done on the original implementation by members of CS 632 at the University of Utah, namely David Anderson, Kay Brown, Duane Call, Patrick Baudelaire, Roger DeBry, Joe Locascio, Don Vickers, and Martin Yonke.

We would also like to thank Jim Curry and Carl Ellison for *facir* helpful advice and assistance.

TABLE OF CONTENTS

	Acknowledgments	ii
	Abstract	v
Introduc	ion	1
Part I:	The Basic Features of EULER	2
	1. EULER Variables	2
	2. Expressions	3
	3. Statements	4
	3.1. Assignment Statement	4
	3.2. FOR Statement	5
	4. String Manipulation in EULER	6
	5. Arrays and Matrices	7
	6. Lists	8
	7. Procedures	10
	8. Teletype Input and Output	12
	9. EULER Constants	13
	10. Program Formatting and Comments	14
Part II:	How to Use PDP-10 EULER	16
	1. Compiling	16
	2. Loading and Executing	16
	3. Run-Time Errors	17
	4. Debugging Aids	18

r 6. w

Part III: Advanced EULER Programming	21
1. Use of Statement Values	21
2. Procedures	23
3. External and Library Procedures	25
4. File Input-Output	26
5. Coping with Large List-Structures	29
6. Send-Receive	31
Appendix I: Basic Operators	34
Appendix II: EULER Reserved Procedures	36
Appendix III: EULER Library Procedures	37
Appendix IV: Euler D, SEULD	39
Appendix V: List of Error Messages	41
Appendix VI: Euler-G	44
Appendix VII: EULER Compiler Error Messages	56
Appendix VIII: Linking Assembly Code to EULER Programs	57
Appendix IX: Data Formats	61

References

65

iv

INTRODUCTION

EULER is a block-structured language, similar in appearance to Algol but embodying many fresh concepts which make it an easier language to understand and use. The original reason for implementing it on the PDP-10 was to create a language for experimenting with data structures. However, it soon appeared that EULER had many applications as a generalpurpose language with good data-handling and debugging facilities, and this manual has been prepared for people who wish to make use of it as such.

The first thing that must be said about PDP-10 EULER is that it is different from EULER as proposed by Wirth and Weber⁽¹⁾. It contains <u>for</u> statements, arrays as well as lists, and omits <u>go to</u> statements. There are also some major differences in the way it has been implemented, but these are probably not of interest to the general user. Readers familiar with Algol 60⁽²⁾ will have 1ⁱ+¹+¹</sup> difficulty in using EULER, once they have understood the basic differences between the two languages. These are covered in Part I.

EULER programs are executed by an interpreter called SEUL. This interpreter operates on Polish-string object code generated by the EULER compiler. The object code is in the form of six-bit bytes, and some care was taken to make it readable for debugging purposes. A number of other debugging aids have been added to the interpreter which probably make this feature redundant.

Other useful features of PDP-10 EULER are string, list and matrix operations, file input-output and a very straightforward library feature. These are all described in the rest of this report. PART I

THE BASIC FEATURES OF BULER

1. EULL'R Variables

Like most high-level languages, EULER has facilities for handling integers, real numbers, boolean values, strings and arrays. These can all be stored into variables and manipulated in the usual way. However, EULER imposes no restrictions on the type of data that may be stored into a given variable. A single variable may, during execution of a program, successively contain an integer, a real number, a boolean value, a string, an array, a list and a procedure. This contrasts with Algol 60, in which variables are declared to have a certain type when the program is written and during execution can contain only that type of data.

The EULER interpreter avoids this restriction by saving a few extra bits of information with each variable; by using these bits during execution it can determine how the contents should be treated. This of course reduces execution speed. However, it permits mixed types of data to be stored into lists and arrays, and it also reduces the burden on the programmer. EULER variables are declared in a single NEW declaration following the start of a block:

BEGIN NEW A, 21, 22, MAXVALUE;

Any statement between the declaration and the final END may refer to these variables. Outside the block they are meaningless, and any attempt to refer to them will cause an error. The contents of a variable just after it has been declared are undefined. Variable names may be any number of characters in length; all characters are significant.

Variables may be <u>subscripted</u> to address a particular cell in a list or an array or to pass arguments to a procedure:

A[23]
L3[K+1]
MAX[A,B]

Each of the subscripts in the list enclosed within brackets may be any EULER statement or expression: see below for a list of the various types of statement permitted in EULER. Also discussed below is the use of multiple subscripts, such as:

L23[K] [3] [N+5]

2. Expressions

Expressions may be formed from variables, constants and other expressions enclosed in parentheses. The most common type is an <u>arith-</u> metic expression:

A + 3.2 - 100 + (B + C/17)

However, <u>logical expressions</u> are just as useful: they have either <u>true</u> or <u>false</u> values:

> A > BA = 3 OR NOT (B < 17 AND BOOL3)

Expressions may also involve strings, lists or arrays, as described later.

3. Statements

EULER includes most of the types of statements permitted by Algol. These include assignment statements, conditional (IF) statements, FOR statements, and compound statements or <u>blocks</u>. An expression (arithmetic or logical) is a valid EULER statement. GO TO statements and labels are omitted. PDP-10 EULEK also includes some special forms of output statement (PRINT, WRITE) and list manipulation statement (INSEPT, REMOVE).

Δ

3.1 Assignment Statement

An important feature of EULER is that every statement has a <u>value</u>. In most cases this value is not put to any use, but is thrown away after the semicolon which separates statements is passed. For example, the value of the following statement is the sum of the values stored in A and B:

A + B;

By itself, this expression does nothing. Similarly, the following conditional expression may have the value of C or D, but will not affect the state of the program:

IF A > B THEN C ELSE D;

On the other hand, if we incorporate this expression into an assignment statement, as EULER will allow us to do, we can change the program's state:

 $P \leftarrow IF A > B$ THEN C ELSE D;

Here the value of the statement, which is the value of either C or D, is stored into P. EULER allows any statement, with any type of value, to be used as the right-hand side of an assignment statement.

3.2 FOR Statement

The FOR statement provides a basis for most algorithms involving repeated operations. There are several variants of the FOR statement. The FOR-STEP-UNTIL statement allows an operation to be executed a predetermined number of times:

FOR K + 1 STEP 1 UNTIL 10 DO A[K] + 0

This will store zero into cells A[1] to A[10] inclusive. The scope of the DO is limited to one statement:

FOR N + 1 STEP 1 UNTIL 5 DO P + P * N; Q + Q + P

The first statement following DO, "P + P * N", will be executed five times; the second, "Q + Q + P", will be executed only once, following completion of the FOR statement. To cause both statements to be executed after every step, we must include them in a single compound statement:

> FOR N + 1 STEP 1 UNTIL 5 DO BEGIN P + P + N;Q + Q + PEND

WHILE may be used instead of UNTIL or STEP-UNTIL so that looping terminates when a condition is no longer true:

> LOOKING + TRUE; FOR K + 1 STEP 1 WHILE LOOKING DO LOOKING + A[K]#N;

The above will loop through A until a cell equal to N is found.

```
FOR INP + TRUE WHILE INP DO
BEGIN NEW N;
N + INVAL;
ANS + ANS + N
END
```

This example creates an endless loop since INP never becomes false. This type of loop is useful for writing interactive programs in EULER.

Note that there is no semicolon before an END. Semicolons are used only to <u>separate</u> a statement or declaration from the following statement. Errors will occur if this rule is not followed.

4. String Manipulation in EULER

A string of any length may be stored into a variable:

S3 + "THIS IS THE PLACE"

The contents of this variable may then be printed out, concatenated with other strings, or manipulated in various ways. It is not possible to access individual characters in a string. However, any string may be converted to a list of integers, using the reserved procedure UNSTRING:

L7 + UNSTRING[S3]

Each cell in the list L7 will receive one character, converted into an integer representing the appropriate ASCII code. The reverse operation is also permitted:

S2 + STRING[N]

N may be a list or array of integers or just a single integer. A string is formed of all the codes up to the first zero or non-integer.

5. Arrays and Matrices

EULER arrays are similar to FORTRAN arrays in that the lower bound is always unity. However, EULER arrays may have any number of dimensions. They are created as follows:

A + ARRAY [2, ASIZE]

and may be accessed as follows:

$$A[1, J+1] + 2$$

Any type of information may be stored in any array cell, including another array:

A3[10] + "JOHN SMITH"' A3[11] + TRUE; A3[14] + ARRAY[20];

An array stored in a cell of another array can be accessed by <u>double</u> subscripting:

X + A3[14][N]

Two-dimensional arrays may be treated as <u>matrices</u>. The interpreter is able to carry out matrix multiplication and addition:

A ← ARRAY[2,3]; %A becomes a matrix with 2 rows of 3 cells%
B ← ARRAY[3,4];
.....
C + A * B;

This will create a new array C, whose dimensions are 2x4, containing the matrix product of A and B. Matrices may be scaled:

$$A \leftarrow ARRAY[1,4];$$

.....
 $A \leftarrow A/A[1,4];$

Matrices may contain integer or real values in any mixture. The result of a matrix operation leaves all the contents real.

6. Lists

Wirth's original description of EULER includes list-processing operations, and with a few minor changes these have been implemented

in PDP-10 EULER. Figure 1 shows
an EULER list, stored into a
variable L. Cells in this list
can be accessed in the same way
as array cells: for example,
L(1)=3.6, L(2) ="ABC", L(4)=123.
L(3) is itself a list, and its




Figure 1

cells can be addressed by double subscripting: L[3][1]=TRUE, L[3][2]=0.0.

There are three principal ways of constructing a list:

1.) By explicitly defining its contents:

L+[3.6, "ABC", [TRUE 0.0], 123]

2.) By defining the list and later defining its contents:

L+LIST[4] L[1]+3.6; L[2]+"ABC"; L[3]+LIST[2]; L[4]+123; L[3][1]+TRUE; L[3][2]+0.0;

3.) By concatenating existing lists:

L1~[3.6,"ABC"]; L2~[TRUE,0.0]; L3~L1&[L2]&[123]

The expression [] can be used to indicate an empty list. Wirth's two other operations, LENGTH and TAIL, are also included. LENGTH allows the number of cells in a list to be determined:

> LENGTH [L] ≡ 4 LENGTH [L [3]] ≡ 2

TAIL removes the first element from a list:

TAIL[L] : ["ABC", [TRUE,0.0],123] TAIL[TAIL[L] [2]] [1] =0.0

PDP-10 EULER also includes two special statements, INSERT and REMOVE, to make list operations more efficient. INSERT has four variants:

- a) INSERT L1 BEFORE L2
- b) INSERT L1 AFTER L2
- c) INSERT L1 BEFORE L2:N
- d) INSERT L1 AFTER L2:N

(a) and (b) add list L2 to list L1, respectively before the first and after the last element of L2. (c) and (d) permit additions to be made anywhere within a list--N is an index into L2, and can be any

```
INSERT ["ABC", [TRUE, 0.0]] AFTER [3.6,123]:1
```

REMOVE has only one form:

REMOVE L:N

which removes the Nth element of list L. Thus REMOVE L:l is equivalent to L+TAIL[L].

The value of the INSERT statement is the resultant list structure. REMOVE returns as value the removed element.

7. Procedures

One of the most attractive features of EULER is its handling of procedures. Basically, a procedure may be assigned to any variable; then whenever that variable is accessed, the procedure will be executed. Procedures may be stored into cells of an array or list. The way in which procedures are defined is as follows:

OUTAB+'PRINT A; PRINT B'

All the statements included within quotes are executed when the procedure is accessed. Arguments may be passed to procedures by the use of subscripts; there must be a <u>formal declaration</u> at the start of the procedure, listing all the parameters to be passed:

> MAX + 'FORMAL A,B; IF A>B THEN A ELSE B'; X+MAX [J, 3*P-17];

The mechanism of calling procedures in EULER is quite different from that in Algol. Unless specified, parameters are passed by <u>value</u>. Each of the expressions in the subscript list is evaluated, and each of these values is assigned to a formal variable, starting with the first. Thus in the example above, A would receive the value of J, B the value of the expression 3*P-17.

Calls by <u>name</u> are achieved by enclosing the arguments within quotes. Consider the following example:

A+0; PRINT2+'FORMAL X; X+2; PRINT X'; PRINT2[A]; PRINT2['A'];

PRINT2[A] merely prints the number 2: since it is called by value, the contents of A are not changed. PRINT2['A'] on the other hand is a call by name, hence all references within PRINT2 to the formal X are treated as references to A. At the end of this second call, A contains the value 2.

The value returned by a procedure is the value of the last statement executed within the procedure. Thus the value of the above procedure MAX is the value of the IF-expression. Procedures may also be thought of as returning an <u>address</u>. For example:

> CELL3+'A[3]'; CELL3+22; B+CELL3;

This example defines an "access procedure" which allows data to be stored into or read out of A[3] as if CELL3 were a simple

variable. Note that when a procedure is stored into a variable, that variable becomes "execute only" and no other contents can replace the procedure.

Arrays, lists and strings may be passed as arguments to a procedure. For example, the following procedure ZMATRIX will create a two-dimensional array of the required dimensions, with all cells set to zero:

> 2MATRIX+'FORMAL M,N; BEGIN NEW A,J,K; A+ARRAY[M,N]; FOR J+1 STEP 1 UNTIL M DO FOR K+1 STEP 1 UNTIL N DO A[J,K]+0;

> > END'

A

and can then be called as follows:

ROTN+ZMATRIX[3,3]

8. Teletype Input and Output

The INPUT statement in EULER reads one character from the teletype. If nothing has been typed, the program waits until a character is typed. The value of INPUT is an integer, representing the ASCII code of the character typed. It may be converted to a singlecharacter string with the STRING operator:

IF STRING [INPUT] = "G" THEN PROGO

The INPUT statement has seer incorporated in a number of library procedures for input of numbers and text (see Appendix III).

Output to the teletype is achieved by using the PRINT statement:

PRINT A; PRINT "ANSWER IS", X23

Any number of arguments may be listed in a PRINT statement, and their values may be of type integer, real or string. Numbers are printed out in a fixed format. Programmers may define their own format as follows:

> PRINT A, B IN "A= W B= \\.\\"; FMT+"ANGLE IS \\.\ DEGREES"; PRJNT 180*THETA/P1 IN FMT;

Each item in the output list of a formatted PRINT statement will be inserted in a field of the format; these fields are indicated by back-slashes. A period will cause numbers to be converted to floating-point notation--otherwise integer notation will be used. Positive values are left unsigned unless a sign position is indicated:

PRINT X1, X2 IN "+\\\ +\\\"

9. Euler Constants

Constants may be integers, real numbers, or strings. Any number including a decimal point is treated as real. Any text enclosed within double quotes is stored as a string. The compiler will not accept certain characters within strings, so the following conventions are used:

'В	bel	1

'C carriage return

'F form feed

'L line feed

'N carriage return - linefeed

'S space

'T tab

single quote

10. Program Formatting and Contents

Spaces, tabs, and carriage-return/line-feeds may be inserted anywhere in the source program except within a symbol or operator, or within a string enclosed in double quotes. The program may therefore be indented by means of spaces and tabs, as illustrated by most of the examples in this manual.

Wherever a space, tab, or carriage-return/line-feed is permitted, a <u>commert</u> may be inserted by enclosing it within percent symbols:

IF A > B THEN %EXCHANGE A AND B%
BEGIN NEW T; %T 1S TEMPORARY VAR%
T ← A; A ← B; B ← T %EXCHANGE COMPLETE%
END;

Comments may extend to more than one line.

The complete program should be enclosed within a BEGIN...END pair. This first BEGIN must be followed by a declaration, and preceded by a <u>title</u>, which is any symbol:

TITLE	PRO	3 3		
BEGIN	NEW	X,	Υ,	P;
•••	•••			
•••	•••			
END				

PART II

HOW TO USE PDP-10 EULER

1. Compiling

Source programs should be prepared and filed in the usual way with QED or TECO. They can then be compiled in the following manner:

> .R EULER * *DEV:FNAME1.EXT+DEV:FNAME2.EXT

or the following shorter form may be used:

.R EULER *XXXX+XXXX

This assumes that the source file is XXXX.SRC and is on the disk. An object file called XXXX.MAC is created, also on the disk. Users are encouraged to use this form since the EULER debugging routines rely upon these file-name conventions.

2. Loading and Executing

EULER programs are not compiled into machine code and loaded in the conventional manner. Instead they are interpreted by a program called SEUL*. User: should type

.R SELL

*Non-French speakers: this is inpronounceable. The closest approximation is SERL. and then type the name of the object file produced by the EULER compiler:

.R SEUL

If the device name is omitted, DSK is assumed; if both device name and extension are omitted, DSK and .MAC are assumed. Provided the normal file-name conventions are used, the following is therefore sufficient:

.R SEUL

Loader switches are provided to request special action during loading. These may be typed at any point in the file name.

/υ	prints out all undeclared variables
	after loading. These include ex-
	ternal and library procedures.
/B	program enters EULER DDT after loading.

Example:

.R SEUL *PROG/U

Unless the /B switch is used, the program proceeds to execute as soon as loading is complete. A carriage-return/line-feed is output to the teletype as execution commences.

3. Run-Time Errors

If an error is detected during execution, the following happens:

- i) An error message is printed on the teletype;
- ii) The statement in the source file in which the error occurred is printed;
- iii) The program returns to the monitor.

We have tried to ensure that the source statement printed out is indeed the statement in which the error occurred. However, the technique we have used takes some short cuts to avoid complete recompilation of the program. On occasions, several statements will be printed if SEUL cannot determine the precise statement in which the error occurred. A list of error messages will be found in Appendix V.

4. Debugging Aids

Debugging aids fall into two categories:

- i) Facilities to print out the state of the program;
- ii) Facilities to set break-points so that execution is interrupted at a certain point.

Whenever a run-time error occurs, the contents of any active variable may be printed out. To do this, type REENTER (or REE for short). The program should respond with an asterisk, and you may then type the name of any active variable, followed by a slash. If the variable is inactive, "U?" will be printed in an appropriate format. The following are some examples of printouts from EULER DDT:

REE	
*VAL/	231
*K/	5.60017
*NAME/	"JOE"
*FOUND/	TRUE
*XYZ/	UNDEF

Variables to which procedures have been assigned, and formal variables called by name, simply print out as "PROC". Similarly arrays and lists print out as "ARRAY" and "LIST". You may however access individual array and list cells by adding a subscript or subscripts to the name:

To print out the entire active stack contents, type:

./

Break-points may be set prior to execution by using the /B losser switch. After loading is complete an asterisk is printed, and up to eight break-points may then be set in the program. Wherever possible this feature uses the conventions of PDP-10 DDT.

To <u>set</u> a break-point, type a line number in the source code followed by \$nB (\$ = alt-mode; n is the break-point number, 1 to 8). The break-point will be set at the first "store" operation in that line. For example, if the following is line 27 of the source program, and 27\$1B is typed, the program will break before storing 33 into A:

A+33; B+A+5;

To cause breaking on the second or successive "store" operations, you may type:

63

27,2\$1B or 27,3\$1B etc.

The integer following the comma indicates to which of the "stores" the break-point is to be attached. If this number exceeds the number of assignments on the line, a statement will be chosen in the lines following. The break-point number, n, may be omitted. In this case numbers are assigned automatically, starting at 1. To clear a break-point type Ø\$nB. To clear all break-points, type \$B.

To print out the contents of any line, type the line number, followed by a slash:

27/

The most recent line typed can be referred to as ".", and other lines may be addressed relative to it:

27/	prints line 27
.+1/	prints line 28, . becomes 28
.,1\$B	sets a break-point at the first "store" in line 28
5,2\$B	sets another break-point at the second "store" in line 23
. 2/	prints line 30 (space and + are equivalent)

As in PDP-10 DDT, line-feed and .+1/ are equivalent, and so are \uparrow and .-1/.

To start execution, type \$G. The program will execute normally until a break-point is encountered. Then execution will cease, and the break-point number, together with the value just about to be stored, will be printed:

3B >> Ø.Ø1753

You may now examine variables and set or clear break-points, as described above. To resume execution, type SP.

PART ITI

ADVANCED EULER PROGRAMMING

This section is devoted to some of the more refined techniques in EULER programming, and to some of the facilities in the language which were not described in Part I.

1. Use of Statement Values

It is frequently possible to take advantage of the fact that statements possess values. An example was given earlier in Part I. More elaborate examples are discussed here.

When matrices are being used, it is sometimes necessary to create a new matrix with its cells set to certain initial values. Suppose we wish to store into A either the matrix currently in B or, if B is undefined, a 3x3 unity matrix. This can be done as follows:

> A*-IF TYPE[B] = 4 THEN B ELSE BEGIN NEW T,J,K; T*-ARRAY[3,3]; FOR J*1 STEP 1 UNTIL 3 DO FOR K*-1 STEP 1 UNTIL 3 DO T[J,K]+IF J=K THEN 1 ELSE 0; T

> > END .

This example makes use twice of the values of IF statements. Another technique that may be used with IF statements is the <u>compound</u> <u>logical expression</u>. The expression following "IF" may be <u>any</u> expression whose value is <u>true</u> or <u>false</u>. An expression may be any statement or statements enclosed within parentheses*, so the following is permitted:

IF (A+B[X]; A>O) THEN Q+A

Since all the statements within parentheses are executed before the test is carried out, this provides a method of including unconditional statements in chains of IF statements (IF...THEN... ELSE IF...THEN...ELSE IF...) without the use of BEGIN and END:

IF(X+X-1;A[X,Y]=0) THEN TRUE ELSE
IF(X+X+1;Y+Y+1;A[X,Y]=0) THEN TRUE ELSE
IF(X+X+1;Y+Y-1;A[X,Y]=0) THEN TRUE ELSE
(X+X-1;Y+Y-1;A[X,Y]=0)

The above statement finds whether any cell adjacent to (X,Y)in the matrix A contains zero, and if so returns with X and Y set to the position of the first such cell it finds.

Difficulties often arise with IF statements because all parts of a complex logical expression are evaluated before the test is applied (this is out of line with Wirth's proposals). In a statement of the form IF L1 AND L2 THEN A ELSE B the evaluation of L2 may cause an error if L1 has the value <u>false</u>. One solution is the nested IF statement:

> IF L1 THEN BEGIN IF L2 THEN A END ELSE B

* Note that parentheses () are equivalent to BEGIN END

The BEGIN is necessary here since the second IF statement does not include an ELSE clause, but the first one does. Another correct version is:

IF L1 THEN IF L2 THEN A ELSE B ELSE B

and the following will also work:

IF(IF LI THEN L2 ELSE FALSE) THEN A ELSE B

2. Procedures

Part I mentioned that variables into which procedures have been stored become "execute only." This means that it is not possible successively to store different procedures into a variable as follows:

> $p \leftarrow 'IF N=0$ THEN A ELSE B'; $p \leftarrow 'A \leftarrow B \leftarrow 0';$

Whenever a procedure variable is accessed, the procedure is called immediately; so the example above will succeed only in storing the second procedure into either A or B.

The only way to replace one procedure by another is to reclaim and re-allocate the space it occupies. This is difficult to do with ordinary variables, since a variable is only reclaimed when the end is reached of

the block in which it was declared. With lists and arrays, however, it is easier to do. Suppose we wish to build a list L in the form shown in Figure 2.




Figure 2

Each element of L is itself a list, which contains in the first element a procedure indicating what to do with the following two elements. If we wish to change the procedure, leaving the rest of the sub-list unchanged, we can do do by discarding the first element and then redefining it. For example:

> L[K]+LIST[1] & TAIL[L[K]]; L[K][1]+'FORMAL A,B; A+B';

We may now "evaluate" any sublist K in the following manner:

VAL+L[K] [1] [L[K] [2], L[K] [3]]

The concept of <u>recursive procedures</u> is widely understood and used. All EULER procedures may be called recursively. However, if the number of nested calls exceeds 30, stack overflow will occur. To illustrate the use of recursion, here is an example taken from the EULER library file:

> TITLE SINE 'FORMAL X; BEGIN NEW PI; PI+3.14159; IF X>=0 THEN BEGIN IF X<0.1 THEN X-(X⁺3)/6 ELSE IF X<=PI/2 THEN 2*SIN[X/2]*SQRT[1-SIN[X/2]+2] ELSE IF X<=PI THEN SIN[PI-X] ELSE SIN[X-2*PI] END ELSE -SIN[-X] END'

One of the original ideas behind PDP-10 EULER was the concept of using procedures as <u>access functions</u>. It is possible to use procedures to attach names to specific list or array elements, and

to store into and read out of these elements by means of their names:

```
BEGIN NEW A, LENGTH, HEIGHT, WIDTH, K, J;
A+ARRAY[100,3];
LENGTH+'FORMAL X; A[X,1]';
HEIGHT+'FORMAL X; A[X,2]';
WIDTH+'FORMAL X; A[X,3]';
.....
LENGTH[K]+INVAL;
.....
IF LENGTH[J]=0 THEN...
```

The above example makes LENGTH[X] synonymous with A[X,1]. Notice the use of EULER's block structure to pre-empt a "reserved" procedure name, i.e., LENGTH. Within the block in which LENGTH is declared the user's procedure will take precedence over the reserved LENGTH procedure which determines lengths of lists and arrays. Users who feel they can improve upon the EULER library procedures can pre-empt them in the same way, as described below.

3. External and Library Procedures

.

EULER programs may be written as external procedures by adopting and following slightly modified syntax:

TITLE EXTPROC		TITLE	EXTPROC
'FORMAL F1, F2;	or	•	• • • •
		• • • • •	• • • '

A complete example is shown above in the sine procedure. External procedures may be called from other programs without declaring them. The

interpreter assumes that every undefined variable is an external procedure and attempts to find it on the disk as follows:

a) by looking it up on the users area with extension .MAC;

b) by looking it up on his area with extension .EUL;

c) by looking it up under [1,1] with extension .EUL.

If all of these fail, an error message is printed. This order of precedence is useful in a number of ways. For example, if a program has been designed to be controlled by the mouse, and the user wishes to test it from the teletype, he can do so by writing his own external MOUSE procedure and filing the object code on his disk area as MOUSE.MAC or MOUSE.EUL. The following procedure would allow him to type in a switch number and two coordinates, and to the program would be indistinguishable from library MOUSE procedure:

> TITLE MOUSE 'BEGIN NEW SN; SN+INVAL; IF SN=1 THEN (TRUE, FALSE, FALSE, INVAL, INVAL) ELSE IF SN=2 THEN (FALSE, TRUE, FALSE, INVAL, INVAL) ELSE [FALSE, FALSE, TRUE, INVAL, INVAL]

END'

4. File Input-Output

EULER programs may read and write standard PDP-10 text files. For this purpose, a WRITE statement and a reserved procedure called READ have been added. They operate in a fashion exact, analogous to PRINT and INPUT:

CH+READ;

CH as an integer \$

WRITE statements may include format specifications.

In order to make use of READ and WRITE, the programmer must include statements to open and close files. If you are going to write a file, you must open it for output:

OUTFILE ["DSK", "FNAME", "EXTN"];

After all output is complete, the file is closed for output:

OCLOSE;

Since only one file at a time may be opened for output, the OCLOSE statement requires no arguments. Existing files may be opened for input and later closed as follows:

> INFILE["DSK", "FNAME", "EXTN"]; ICLOSE;

During input it is possible to check whether the end of the file has been reached by using EFILE. This will return true if the end has been reached, otherwise it will return false:

IF EFILE THEN ICLOSE ELSE CH (K+K+1)+READ

Arguments for INFILE AND OUTFILE may is given as shown above, i.e., as a separate string for device name, file name, and extension. Other

combinations of arguments are permitted, and the complete list is as follows:

It is of course permissible to use any string as device name, file name, or extension, although names that are too long will be truncated. The following program will write out successive cells of the list LTEXT as files called LTEXT.001, LTEXT.002, etc.:

```
FOR K+1 STEP 1 UNTIL LENGTH [LTEXT] DO
BEGIN
OUTFILE["LTEXT",STRING[[K//100+48,(K MOD 100)//10+48,K MOD 10+48]]];
WRITE
OCLOSE
END
```

File input-output will work successfully for the following physical devices:

DEK	
DTAS-DTA7	
PTP]	a dummy file-name and extension must
PTR	be given
TTY	De given

5. Coping with Large List-Structures

Almost any program that makes use of lists will tend to produce large structures. This raises two problems:

- a) It becomes very tedious to examine and debug these structures;
- b) The program will eventually grow too big to be accommodated in core.

With these problems in mind, two features have been added to EULER. One is a library procedure call WRLIST. It will write out a text file listing all the contents of a named list, making it possible to examine the contents. It is called as follows:

WRLIST["DEV", "NAME", "EXT", LISTNAME]

LISTNAME is the variable containing the list. The resultant text file looks something like this:

[CELL1, CELL2, CELL3.....CELLN];

where CELL1, CELL2, etc., are the contents of each cell. These contents are written out in a format appropriate to the data type, for example:

[3.6, "ABC", [TRUE, 0.0], 123]

This is the WRLIST output of the list structure shown on page 8.

Since WRLIST can output arrays, it provides a convenient means of dumping out the entire contents of an array without using FOR statements:

WRLIST["TTY", "X", "X", [A]]

There is currently no RDLIST procedure to read in the results of WRLIST. To cope with this need, and with the second problem mentioned above, the EULER interpreter has been extended to permit the reading and writing of lists in library format. The principal value of this is to permit the use of secondary memory for storing data, as follows:

SWAPOUT ["XXX", L1];	will write out Ll onto the disk as a file called XXX.
L1+SWAPOUT["XXX", L1];	will do the same, and will reclaim the storage occupied by Ll.
J+LLNGTH [L1];	will cause Ll to be read back in from XXX.
L2+SWAPIN["XXX"]	will perform the equivalent of stor

will perform the equivalent of storing the original contents of Ll into L2. The actual operation will not take place until L2 is referenced, e.g., by LENGTH [L2].

Thus, after a list has been swapped out, it can still be accessed and modified as if it were in core--the very next access will automatically bring it back in. SWAPIN and SWAPOUT use the same file-name argument conventions as INFILE and OUTFILE, except for the additional final argument to SWAPOUT.

5. Send-Receive

If two EULER programs are running simultaneously, they can communicate via <u>send-receive</u>. Send-receive perhits programs to do the following:

- a) to announce their <u>name</u> for the purpose of sending messages to and receiving them from other jobs;
- b) to send a message to another job of known name;
- c) to wait for a message from another job;
- d) to determine whether a message has been received from another job, and if so to determine the name of the sender and the message contents.

A process name may be any text string. For example:

"WILLIAM" "MASTERPROCESS"

are valid names for processes. A program announces its name to the outside world by the following procedure call:

DECLARE ["JOE"]

After declaring its name, a program may send a message to another program whose name it knows:

SEND["PETE", MSG]

A message may be one of the following:

- i) an integer in the range 0 to 250,000
- ii) a text string
- iii) a list

To receive a message, a program calls:

X+RECEIVE ("JOE")

This will be executed immediately, and will store into X:

- a) an empty list, if no message has been received;
- b) a two-element list, [sender, message], if a message has been received from the requested sender;
- c) a single-element list, [sender], if the requested sender sent nothing, but another sender, whose name is now returned, has sent a message. A second RECEIVE is necessary to determine his message.

RECEIVE[0] will receive a message independent of its sender. In this case the name of the sending process may be not a string but a list containing two integers. If you wish the program simply to halt until a message is received, you may use RECWAIT. RECWAIT ("JOE") will cause the program to halt until a message is received from process JOE. MECWAIT[0] waits until a message is received, irrespective of the sender. The willows returned by RECWAIT and RECEIVE are identical.

As an example of the use of send-receive, suppose that we wish to allow two terminal users to send messages to each other without using the standard TALK facility of the PDP-10. The following program will handle each end of such a conversation:

> TITLE SR BEGIN HISNAME, RUNNING; PRINT "TYTE YOUR NAME:"; DECLARE [INTEXT]; • declares typed string as name of process • PRINT "TYPE DESTINATION:"; HISNAME* INTEXT; PRINT "DO YOU WISH TO WAIT FOR A MESSAGE?";

```
IF INTEXT # "Y" THEN % send a message %
SEND[HISNAME,INTEXT];
FOR RUNNING TRUE WHILE RUNNING DO
BEGIN
% wait for a message %
PRINT RECWAIT[HISNAME][2]
% when received, print it %
SEND[HISNAME,INTEXT]
% send another %
```

```
END
```

END

APPENDIX I.

BASIC OPERATORS

Symbol	Meaning	Operan	ds
+	unary plus	scalar	-
	addition	scalar	scalar
		matrix	matrix
-	unary minus	scalar	1.1
	subtraction	scalar	scalar
		matrix	matrix
*	multiplication	scalar	scalar
		matrix	matrix
		matrix	scalar
/	division	scalar	scalar
		matrix	scalar
11	integer division	scalar	scalar
+	exponentiation	scalar	integer
MOD	modulus	scalar	scalar
	e.g., A MOD 3		
ABS	absolute value	scalar	
	e.g., A + ABS B		

>	greater than		
<	less than		
>=	greater than /equals	scalar	scalar
<=	less than /equals		ocurar
	equals	string	string

boolean

boolean

NOT complement integer boolean AND logical intersection integer boolean OR logical union integer boolean concatenation 8 string string list list

Precedence is as follows, in descending order:

not equals

ABS + - (unary) * / // MOD † & + - (binary) > < >= <= = # NOT AND OR

APPENDIX II

EULER RESERVED PROCEDURES

ARRAY [M,N]	creates an array with dimensions M,N
EFILE	checks for end-of-file, returns true/false
EXIT	program returns to the Monitor
ENTIER(N)	makes an integer
ICLOSE	closes file after input
INFILE()	opens file for input
INPUT	inputs one character from teletype
LENGTH [L]	returns the length of a list, array, or string
LIST [N]	creates a list of N cells
OCLOSE	closes file after output
OUTFILE []	opens file for output
READ	reads one character from file
STRING[L]	converts list, array or integer to string
TAIL(L)	removes the first cell of a list
TYPE (V)	returns the type of argument V:
	-1 means undefined
	O means real
	1 means integer
	2 means boolean
	3 means string
	4 means array
	5 means list
UNSTRING(S)	converts string to list

APPENDIX III.

EULER LIBRARY PROCEDURES

DECLARE SEND RECEIVE RECWAIT

INSTRING

INTEXT

INVAL

INVERT

MOUSE

See Part III., Section 6.

e.g., LOOKUP[INSTRING] Terminating characters are space, period, = and carriage-return. Identical to INSTRING, but carriagereturn is the only terminator. Reads in one signed integer or floatingpoint number from the teletype.

Reads in ; text string from the teletype.

e.g., X+INVAL

Terminating characters are comma, space or carriage return.

Will invert a matrix

e.g., M1+INVERT[M2]

Reads the status of the mouse or tablet next time a switch is pressed. Returns as value a five-element array, containing: in element 1: switch 1 setting (true or false)

> in element 2: switch 2 setting in element 3: switch 3 setting

in element 4: x-coordinate (integer in range 0-1023)

in element 5: y-coordinate (integer in range 0-1023)

Note that when the Sylvania tablet is in use, switches 1, 2 and 3 are turned on (=true) progressively in that order as the stylus approaches the tablet surface. e.g., M+MOUSE;

IF M[1] THEN (X+M[4]; Y+M[5]) Returns a pseudo-random number in the range 0 to 1.0.

e.g., X+RANDOM

Trigonometric functions. Angles are assumed to be in radians.

Identical to MOUSE, but the coordinates are scaled to lie in the range -1 to +1. Square root function.

Writes out a text file representation of any list; useful for debugging. The file may be written out onto the teletype.

e.g., WRLIST["DSK", "FNAME", "EXT", L];

WRLIST ["TTY", "X", "X", L]

These will write out the list L onto a disk file called FNAME.EXT and onto the teletype, respectively.

RANDOM

SIN COS ARCTAN

SMOUSE

SQRT

WRLIST

APPENDIX IV.

EULER D, SEULD

Before the appearance of EULER-G a very simple graphic package was implemented for Euler. This package is still available as part of a special interpreter called SEULD. Euler programs which use this system can be compiled by the standard EULER compiler.

The graphical commands are:

POS [X,Y]	<pre>% Position beam to absolute coordi-</pre>
	nates X, Y %
POINT [X,Y]	% Display a point at absolute co-
	ordinates X, Y %
LINE [X1, Y1, X2, Y2]	% Draw a solid line from absolute
	coordinates X1,Y1 to absolute
	coordinates X2, Y2 %
LINETO [X2,Y2]	% Draw a solid line from the present
	position of the beam to the absolute

coordinates X2, Y2 %

All coordinates must be between 0 and 2047. The visible portion of the screen is the lower left quadrant of this area (0,0 to 1023, 1023). Arguments may be integers or floating-point numbers.

To display some text, one may use the command POS[X,Y] to position the beam, followed by DISPLAY X, Y, Z IN F where the DISPLAY statement has exactly the same syntax as the PRINT statement. The format F may be omitted. Characters whose ASCII code is less than 40_8 will be ignored.

The command CLEAR will clear the entire screen.

40

The commands POS, POINT, LINE, LINETO, CLEAR are implemented as external procedures.

APPENDIX V: LIST OF ERROR MESSAGES

004 CANNOT ROTATE 3-D PICTURES 905 "SIZE N" WILL NOT WORK, NO OF DIMENSIONS UNKNOWN 006 "SCALE N" WILL NOT WORK, NO OF DIMENSIONS UNKNOWN MAT NO END OF FILE ON CHARACTER SET 010 STRANGE, FRAME FILE HAS BEEN LOST 011 NO GHARACTER SET FILE FOUND ON DISK 012 CAN'T ENTER FRAME FILE **Ø13 DISK INIT ERROR BI4 OUTPUT ERROR TO STA** 015 STATZ ERROR ON OUTPUT TO DSK 020 CALLING FRAME FROM WITHIN FRAME 021 PARAMETER LIST IN FUNNY SHAPF 222 DISPLAY PARAMETER NOT NUMERIC 023 DISPLAY PARAMETERS MUST BE A LIST 024 NO OF PARAMETERS MUST BE 2 OR 3 025 WINDOW OR VIEWPORT MUST BE SPECIFIED AS A LIST 026 NO OF PARAMETERS MUST BE EVEN 027 WRONG NO OF PARAMS FOR WINDOW OR VIEWPORT 030 TRANSFORMATION MUST BE AN ARRAY 031 TRANSFORMATION ARRAY MUST BE 2-DIMENSIONAL 932 TRANSFORMATION MATRIX MUST BE SQUARE 033 PERMISSIBLE SIZES FOR TRANSFORMATION ARE 2X2,3X3,4X4 037 ASTERISK OMITTED FROM FRAME PROCEDURE DEFINITION 040 VALUE LEFT FOR JUMP-ON-FALSE NOT BOOLEAN 041 WRONG NO OF WINDOW ARGUMENTS 042 WRONG NO OF POSITION ARGUMENTS 643 WRONG NO OF SIZE ARGUMENTS 944 WRONG NO OF SCALE ARGUMENTS 045 CANNOT DEFINE BOTH SIZE AND SCALE 046 ERROR IN PASSING DISPLAY ARGUMENTS 047 WRONG SIZE OF MATRIX FOR TRANSFORMATION 253 CANNOT ROTATE AND TRANSFORM IN SAME DISPLAY CALL 051 CANNOT ROTATE 3-D PICTURE 852 SCALXY AND RELSCALE DO NOT WORK YET WITH ROTATIONS TRANSFORMATIONS ARE NOT PERMITTED IN FRAME PROCEDURES 053 054 "HIT" SHOULD HAVE 3 ARGUMENTS: X, Y, NAME 056 SCALE SHOULD NOT BE DEFINED IN FRAME PROCEDURE **#57 ROTATIONS CANNOT BE DEFINED IN FRAME PROCEDURES** 067 HUH? SINE RTN ASKED FOR SORT OF NEG NO 070 THIS DISPLAY OPERATION NOT YET IMPLEMENTED, SORRY 372 LINE ARGUMENTS MUST BE PASSED AS LIST 073 WRONG NO OF LINE PARAMETERS FOR CURRENT NO OF DIMS **W77 ILLEGAL INSTRUCTION CODE** 100 TOO MANY BLOCK LEVELS 101 TOO MANY VARIABLES DECLARED AT THE SAME LEVEL 102 STACK IN ABNORMAL STATE AT "END" 103 DISPIAY REGISTER UNDERFLOW ON "FND" 104 UNKN WN DESCRIPTOR IN FETCHED VARIABLE ADDRESS WORD FOUND IN PLACE OF VARIABLE 135 RETUR IGG DOWN-POINTER FOUND IN PLACE OF VARIABLE 107 SAVED DISPLAY REGISTER FOUND IN PLACE OF VARIABLE 110 NEW TOP DISPLAY REGISTER FOUND IN PLACE OF VARIABLE III SPECIAL ARRAY DESCRIPTOR FOUND IN PLACE OF VARIABLE 112 NO ADDRESS POINTER FOUND ON STORF 200 NOT A PROCEDURE EXECUTING CALL

42

201 NUMBER OF PROCEDURE ARCUMENTS NOT INTEGER 202 TOO MANY ARGUMENTS IN CALL 203 NO RETURN ADDRESS FOUND ON RETURN FROM PROCEDURE 204 NO SAVED TOP DISPLAY REGISTER FOUND (P.RSTR) 205 CALL INSTRUCTION EXECUTED UNEXPECTEDLY 206 NO SAVED TOP DISPLAY REGISTER FOUND (P. PRIM) 210 NO DOWN POINTER FOUND ON STACK 301 CAN'T EXPONENTIATE BY NON-INTEGER 310 NON-NUMERIC ARGUMENTS FOR ADDITION 312 NON-NUMERIC ARGUMENTS FOR SUBTRACTION 314 NON-NUMERIC ARGUMENTS FOR MULTIPLICATION 315 DIVISION BY ZERO 316 NON-NUMERIC ARGUMENTS FOR DIVISION 317 NON-NUMERIC ARGUMENTS FOR EXPONENTIATION 336 MOD ERROR 340 "OR" ERROR 342 "AND" ERROR 344 "NOT" ERROR 346 NON-BOOLEAN IN BOOLEAN OPERATION 347 NON-BOOLEAN IN BOOLEAN OPERATION 350 NON-NUMERIC ARGUMENT FOR ABS 352 NON-NUMERIC ARGUMENT FOR COMPLEMENT 360 MATRIX OPERATIONS APPLY ONLY TO 2-DIMENSIONAL ARRAYS 361 ILLEGAL OPERATION ON MATRICES 362 MATRICES WRONG SIZES FOR MULTIPLY 363 MATRIX CONTAINS NON-NUMERIC DATA 364 MATRICES OF DIFFERENT SIZES, CANNOT BE ADDED OR SUBTRACTED 377 UNIMPLEMENTED MATRIX OPERATION 500 NUMBER OF ITEMS IN OUTPUT LIST NOT INTEGER 501 ILLEGAL TYPE OF ITEM IN OUTPUT LIST 502 WRONG FORMAT FOR STRING OUTPUT 503 TOO FEW ITEMS IN OUTPUT LIST COMPARED WITH NUMBER OF FIELDS 540 WRONG NUMBER OF ARGUMENTS IN A POS, LINE OR POINT CALL 541 ARGUMENT OF POS, LINE OR POINT IS NOT A NUMBER 542 POS, LINE OR POINT WAS CALLED WITHOUT ARGUMENTS 551 DEVICE NOT AVAILABLE 552 NO FILE NAME GIVEN 553 FILE NOT FOUND 554 TGO MANY NEW VARIABLES OR FORMALS 555 TOO MANY BLOCK LEVELS 557 TOO MANY EXTERNAL VARIABLES 600 ILLEGAL INSTRUCTION FORMAT FOR ARRAY DEFINITION 601 ARRAY DIMENSION VALUE NOT AN INTEGER 602 WRONG TYPE OF VARIABLE USED FOR ARRAY CALL 603 NON-INTEGER USED IN ARRAY DEFINITION 604 NUMBER OF ARRAY DIMENSIONS NOT AN INTEGER 605 INCORRECT NUMBER OF ARRAY DIMENSIONS 606 ARRAY DIMENSION VALUE NOT AN INTEGER 607 SUBSCRIPT NOT AN INTEGER 610 SUBSCRIPT OUT OF RANGE 700 BAD DYNAMIC VARIABLE PASSED TO INTERPRETER 701 SYS ERR - BAD NUMERIC FORMAT 702 FILF NAME ENTER ERROR 703 FILE NAME LOOKUP ERROR 704 OUTPUT DEVICE INITIALIZATION ERROR

705 INPUT DEVICE INITIALIZATION ERROR 706 BAD FILE NAME FORMAT 707 OUTPUT CLOSE ERROR 710 INPUT CLOSE ERROR 711 OUTPUT ERROR 712 INPUT ERROR 713 WRONG NUMBER OF PARAMETERS PASSED TO LIST 714 WRONG NUMBER OF PARAMETERS PASSED TO LIST 715 BAD LIST PASSED TO INTERPRETER 716 INDEX TOO SMALL FOR LIST 717 INDEX TOO LARGE FOR LIST 720 WRONG NUMBER OF PARAMETERS PASSED TO SEPROC 721 WRONG NUMBER OF PARAMETERS PASSED TO TAIL 722 WRONG TYPE OF PARAMETERS PASSED TO CONCATINATION 723 WRONG TYPE OF PARAMETERS PASSED TO UNSTRING 724 RESERVED PROCEDURE EXPECTED ONE PARAMETER 725 WRONG TYPE OF PARAMETERS PASSED TO STRING 726 WRONG TYPE OF ARRAY PASSED TO STRING 727 RESERVED PROCEDURE EXPECTED AN INTEGER 730 WRONG TYPE OF PARAMETERS PASSED TO SRPROC 731 RUN UUO RETURNED 732 ENTIER TAKES ONLY ONE PARAMETER 733 ENTIER TAKES ONLY REAL, INTEGER, OR BOOLEAN 734 BAD ARGUEMENTS TO COMPARE I.E. =, <, >, #, >=, <= 776 SYS ERR - JUMP IS TOO LARGE 777 SYS ERR - DICTIONARY OVERFLOW END LEAVE THIS AS LAST LINE PLEASE: ALL FOLLOWING LINES IGNORED

APPENDIX VI

EULER-G

This appendix describes some extensions which have been made to PDP-10 Euler to permit interactive graphics. The extended language, called <u>Euler-G</u>, should not be confused with the library of graphical procedures in SEULD.

Euler-G uses many of the ideas first proposed in Dial [3]. These include the concept of display procedures, and the assumption that all pictures are scaled before being displayed. Euler-G also contains additional features such as the means to specify rotations and viewports and the ability to display projections of three-dimensional objects. These features should make Euler-G considerably more useful than Dial.

Euler-G produces display files for the Univac 1559. These files are created first in a device-independent format, which is converted to 1559 format by a separate transmission program. It is therefore extremely easy to convert Euler-G so as to output to other devices. Work has already begun on a plotter output package.

Basic Graphical Operations

Graphical output is generated by means of a small set of <u>primi</u>tives. The most important primitives are the following:

MOVE	TO P	:	move t	he displa	ay beam (to poin	t P
MOVE	D	:		he displa	-	-	
			tan	ce D fro	n its cu	rrent p	osition
LINE	TO P	:	draw a	line fre	om the cu	urrent	beam
			POS	ition to	point P		


LINE D : draw a line of length D from the current beam position DISPLAY T1, T2... : display text items T1, T2... at the current beam position

The remaining primitives are variants of LINE TO and LINE which

produce different line textures:

ZIP TO P J	the corners between lines are slightly
ZIP D	rounded. Useful for drawing curves.
DOT TO P	to draw dotted lines
DOT D]	

All points and distances must be specified by <u>lists</u>. These lists must have either two or three elements, depending on whether two-



dimensional or three-dimensional objects are being defined. For example:

MOVE TO (100,150); LINE TO (200,250)

will draw a line from (100,150) to (200, 250) as shown in Figure 1.

Figure 1


Instead of a list, the name may be used of any variable which currently contains a list. For example:

> L3 + [10.0, 3.7]; LINE L3;

> > or:

MOVE TO POINTLIST[1];
FOR K + 2 STEP 1 UNTIL LENGTH (POINTLIST] DO
LINE TO POINTLIST(K);

The second example will produce a sequence of connected lines, such as is shown in Figure 2(b), from a list POINTLIST containing their coordinates in the format shown in Figure 2(a).




The DISPLAY statement is modeled on the Euler PRINT statement, and produces on the display the same output that PRINT produces on the teletype. The same formatting technique is used:

DISPLAY A, B IN "A = \\\ B = \\,\\\ "

Page Coordinates and Screen Coordinates


Most display programming systems force the user to define pictures in a fixed coordinate system, the coordinate system of the display screen. This is not the case with Euler-G. Instead pictures are defined in what is called the <u>page coordinate</u> system, and are displayed by transforming the appropriate parts of the picture into screen coordinates. The programmer has a great deal of freedom to specify: (a) the region of the page which he wishes to see on the screen, (b) the transformation which he wishes to apply to the picture, and (c) the region of the screen which he would like the picture to occupy. This does not imply that he always has to take advantage of all this flexibility. The normal procedure is to specify a rectangular <u>window</u> onto the page information, and a rectangular <u>viewport</u> onto the screen. Figure 3 shows an example. All the page information lying within the window will appear on the screen within the viewport;

everything else is eliminated. The statement to define this transformation is the <u>display</u> <u>procedure call</u>, of which the following is an example:



POINTS WITHIN [200,200,100,100] ONTO [0,0,1,1]

POINTS refers to a procedure, which might well be the example given and shown in Figure 2. The window onto POINTS is specified by WITHIN [200,200,100,100], which means that the center of the window is



at (200,200) and that it measures 100 page coordinate units in size, measured from the center to each edge. The viewport has its size from this point. This is the full screen size: rather than use the particular coordinate system of the Univac 1559, Euler-G assumes the screen dimensions to be those shown in Figure 4.

The complete-sequence of instructions for generating a connected-line picture might be the following:

> FRAME1 + *'POINTS WITHIN[200,200,100,100] ONTO [0,0,1,1] POINTS + 'BEGIN NEW K; MOVE TO POINTLIST[1] FOR K+2 STEP 1 UNTIL LENGTH[POINTLIST] DO LINE TO POINTLIST[K] END';

FRAME1;

Note the asterisk preceding the body of the procedure FRAME1. Any display procedure which is not itself called from another display procedure should include this special mark, indicating that it is a <u>frame procedure</u>. Frame procedures have a number of special properties. In the first place, they allow the picture on the screen to be composed of a number of logically separate parts, each of which can be altered or removed without affecting the others. A frame can be removed by means of the DELETE statement:

DELETE FRAME1

It can be altered by changing the data which it accesses, and then calling it again. For example, if we changed the contents of the list POINTS, and then called FRAME1. we should see a new picture representing the new contents of POINTS. Alternatively the window might be changed in order to show a different part of the complete picture.

Display Procedure Calls

It may be useful to call display procedures to several levels. For example, we might wish to define a symbol that appears repeatedly



Figure 5




Figure 6

in a certain picture. Figure 5 shows a symbol commonly used to indicate wind velocity and direction in weather maps. We could define this as a display procedure called WINDSYM, and create a 'weather map' by means of the following statement:

FOR K+1 STEP 1 UNTIL LENGTH [STATIONS] DO WINDSYM AT STATIONS [K]

This assumes that the position of each weather station is held in a list called STATIONS. The result will be a picture such as Figure 6. We can add a rotation to each symbol as follows:

> FOR K+1 STEP 1 UNTIL LENGTH [STATIONS] DO WINDSYM AT STATIONS[K] ROT WD[K]

WD is a list containing the wind directions, measured in radians. Arguments may be passed to display procedures. The number of 'bars' on a symbol could be held in a list called BARS and passed as follows:

> FOR K+1 STEP 1 UNTIL LENGTH [STATIONS] DO WINDSYM [BARS [K]] AT STATIONS [K] ROT WD [K]

The definition of WINDWYM might look something like the following:

```
WINDSYM + 'FORMAL N; N IS NUMBER OF BARS 

BEGIN NEW K;

CIRCLE WITHIN [0,0,1,1] SIZE 1 AT [0,0];

MOVE TO [1,0];

LINE TO [5,0];

FOR K+1 STEP 1 UNTIL N DO

(LINE [1,0];LINE[1,-1]; MOVE [-1,1])

END'
```

CIRCLE is yet another display procedure, possibly written as an external procedure.


The complete range of transformations and other arguments which may accompany a display procedure call are as follows:

Window:	WITHIN + 4-element list
Viewport:	ONTO + 4-element list
Position:	AT + 2-element list
Size:	SIZE + 2-element list or scalar
Scale:	SCALE + 2-element list or scalar
Rotation:	ROT + scalar
Transformation:	TRANS + 2x2 or 3x3 array
Name :	AS + integer or real number

They may be listed in any order. ONTO [a,b,c,d] is equivalent to AT[a, b]SIZE[c,d]. If both size dimensions are the same, a single scalar may be used; the same applies to SCALE. Rotations are measured anti-clockwise in radians. <u>Names</u> have no effect on the picture: they are for use in detecting mouse hits and so forth.

Windows play an important part in reducing processing time. Suppose we have defined the weather map shown in Figure 7, and wish to view just the portion shown by the dotted outline. The program shown

above will test every line of every symbol for visibility, and discard those outside the window. If there are a lot of invisible symbols this will take a lot of time.



We can reduce this time by specifying a window around the symbol:

WINDSYM[BARS[K]] WITHIN [0,0,10,10] AT ... etc.

This implies that we are only interested in the information within the boundary shown in Figure 8(a), and the program can immediately




Figure 8(a)

eliminate those symbols whose boundaries lie entirely outside the main window. In Figure 8(b) this would mean the upper three symbols.




Figure 8(b)

The Use of Names

Names are useful principally for pointing with the mouse. The reserved procedure HIT[x,y] will return a value <u>true</u> or <u>false</u> according to whether any lines or text lie within a small distance of (x,y) on the screen. Usually this information on its own is of little use: we need to know <u>which</u> item lies at (x,y). This is why names are useful.

If, for example, we would like to point at one of the wind symbols on our weather map, we should call each symbol with a unique name:

FOR K+1 STEP 1 UNTIL LENGTH [STATIONS] DO WINDSYM AS K AT ...etc.

When HIT returns a value <u>true</u>, the name of the symbol we were pointing at is in HITNAME.

The x and y values are normally the x and y coordinates of the mouse, in <u>screen</u> coordinates. To determine these values, use the library procedure SMOUSE. This returns a five-element list as its value each time one of the mouse switches is pressed:

M + SMOUSE;

• •

. ..

M[1] IS TRUE IF SWITCH 1 WAS PRESSED, OTHERWISE FALSE M[2] AND M[3] CONTAIN THE SAME INFORMATION FOR SWITCHES 2 AND 3. M[4] AND M[5] CONTAIN X AND Y IN THE RANGE -1 TO +1 %

Usually when HIT is used we would like to restrict its scope to a certain part of the picture. This can be done by passing a <u>name</u> to HIT: this is the name of the procedure call one level above the symbols at which we are pointing. So if we are going to point at windsymbols, we should pass HIT the name of the call to the whole weather map:

MAP + 'BEGIN NEW K;
FOR K+1 STEP 1 UNTIL LENGTH[STATIONS] DO
WINDSYM AS K WITHIN [0,0,10,10] ROT WD[K]
AT STATIONS[K]
END';

FRAME + *'MAP WITHIN W ONTO V AS 100';

FRAME;

M + SMOUSE

IF HIT[M[4],M[5], 100] THEN ...

& HITNAME NOW CONTAINS THE SYMBOL NUMBER &

A second use for names is in converting from screan coordinates to page coordinates. This can be done with the reserved procedure SCALXY. For example

SCALXY [X,Y,100]

would return the position, in the coordinate system of MAP, corresponding to (X,Y) in screen coordinates. For obscure reasons, SCALXY will not return correct values unless the frame containing the procedure call in question has been called at least once.

A reserved variable which may be accessed within a display procedure is RELSCALE. It returns as value the relative scale on the screen of the current "instance" of this procedure, i.e., the ratio of page units to screen units. It returns a list if the scales in the x- and y-directions are different.

Display Procedure Call Syntax

The syntax of display procedure calls permits any sequence of statements within parentheses to be used in place of a procedure variable name. For example, the following is a permissible display procedure call:

(MOVE TO[20,0]; LINE TO [30,30]) AT [X,Y] SCALE 5

This form may be convenient for such things as displaying text messages:

FTEXT + *'(DISPLAY "START") AT [-.1,.9] WITHIN [0,0,100,100]';
FTEXT;

This will display the message "START" near the top center of the screen.

The display procedure call syntax also requires that all display procedures called from a frame procedure are called with a window or a viewport specified.

Displaying Three-dimensional Data

LINE, LINE TO, MOVE, etc. may specify three coordinates instead of two. In this case the third is treated as a z-coordinate. Three-dimensional information may be transformed in the same way as two-dimensional, with the restriction that rotation cannot be specified by ROT. Windows and viewports, other than the final window and viewport specified in the frame procedure, should have six arguments instead of four; scale, size and position lists should contain three elements; and transformation matrices should be 3x3 or 4x4. SCALXY will not work on three-dimensional data.

How to Use Euler-G

A special Euler-G compiler has been written, and can be run as follows:

• PROG+PROG

This assumes the source file of the user's program is on the disk under

the name PROG.SRC. To run the program, type:

.R SEULG

The debugging fsatures of EULER are all included in Euler-G.

Summary

P + '' P LELETE P CLEAR	defines a frame procedure defines a display procedure calls a frame procedure deletes it clears the screen
DP	followed by one or more transformations calls a display procedure. Transformations allowed are:
WITHIN [x,y,w,h] ONTO [x,y,w,h] AT [x,y] SIZE [w,h] SIZE S SCALE [w,h] SCALE S ROT r TRANS t AS n	<pre>window, center (x,y), size 2wx2h viewport, center (x,y), size 2wx2h position size 2wx2h size 2sx2s scale sxs scale sxs rotated r radians anti-clockwise transformed by matrix t name n</pre>
MOVE TO [x,y] MOVE [dx,dy] LINE TO [x,y] LINE [dx,dy] ZIP TO [x,y] ZIP [dx,dy] DOT TO [x,y] DOT [dx,dy] DISPLAY t1,t2 DISPLAY t1,t2 IN f	move beam to (x,y) move beam through distance dx,dy draw line to (x,y) draw line of length dx,dy like LINE TO, zip mode like LINE, zip mode dotted LINE TO dotted LINE display text items t1,t2 display text in format f
HIT [x,y,n]	look for hit under call n at screen position (x,y) , raturn true or <u>faise</u> ; return name in HITNAME
SCALXY [x,y,n]	scale (x,y) from screen coordinates to page coordinates for call n.
RELSCALE	returns relative scale of current display procedure

APPENDIX VII: EULER Compiler Error Messages

Syntax Error 1: Illegal title

- 2: Outermost block must include declarations
- 3: Illegal declaration list
- 4: Illegal formal variable list
- 5: Not a valid statement
- 6: Illegal statement terminator
- 7: Illegal subscript list
- 8: Integer must follow period
- 9: Illegal statement terminator
- 10: No begin or quote following title
- 11: Illegal item in declaration
- 12: Illegal variable following for
- 13: Only unsubscripted variable names allowed in declarations
- 14: For statement expects +
- 15: No expression following + in for statement
- 16: Illegal expression following step
- 17: Illegal expression following until
- 18: Illegal expression following while
- 19: Either until or while must be included in stepped for statement
- 20: Illegal expression as operand to arithmetic test
- 21: No do in for statement
- 22: Illegal operand for arithmetic binary operator
- 23: Illegal expression following if
- 24: No then in if statement
- 25: Illegal expression as operand for not
- 26: Illegal operand following unary + or -
- 27: Illegal statement as item in output list
- 28: Illegal item used as format
- 29: Illegal expression as operand for or
- 30: Illegal expression as operand for and

System Error 8: Null string, not permitted (Use " 'Z ")

127: String extends over more than one line, not permitted (Use 'N)

End of File Input: Compiler reached end of file without finding final end or quote.

Stack Overflow: Too many nested blocks

APPENDIX VIII

LINKING ASSEMBLY CODE TO EULER PROGRAMS

Assembly code may be linked to EULER programs by creating use: procedures. There is provision for up to ten user procedures. They are called UPO through UP9. These procedures may or may not have parameters, but they must return a value. There is also a facility to initialize user procedures when the program starts.

1. Empty User Procedure Macro Source

An empty user procedure macro source called UPROC.MAC is available from the system programmers. This file has the necessary linkage declarations, accumulator and special symbol definitions, and macro definitions. This file should be used to create user procedure files. A copy of UPROC.MAC is included at the end of this appendix.

2. Accumulator Usage

• **

Accumulators which have names starting with T or FREE may be used without the user having to save them. All others in general should not be touched, except as described below. Accumulator 0 should never be used because the macros use it.

3. User Procedure Initialization

When a program starts, control is transferred to UPI\$\$\$. The user may do whatever initialization is necessary and then return control to the interpreter by executing a RET instruction.

4. User Procedures

When a user procedure is called, control is transferred to UPnSSS. When the procedure is complete, control is returned to the interpreter by executing a JRST I.RET if there are no parameters, or a JRST I.BRET if there are parameters.

5. Parameters to User Procedures

Parameters to the user procedures are passed on the WP stack. The value at (WP) is the number of parameters as an integer. (See Appendix IX for data formats.) The value at-l(WP) is the nth parameter through-n(WP) which is the first parameter.

Before the procedure returns control to the interpreter, it should execute the instruction CAL B.PEEL once for each parameter value and once more for the parameter count value.

6. Determining the Data Type of a Value

Two macros are provided to allow the program to determine the data type of EULER values. They are SKDE and SKDN, SKp Descriptor Equal, and SKp Descriptor Not Equal, respectively. The format is:

SKDE address of value, type of value desired.

The types of interest are:

UNDEFINED	D.UNDF
INTEGER	D. INT
REAL	D.FP
BOOLEAN	D.BOOL

STRING	D.STR or D.TSTR
ARRAY	D.ARR or D.TAR
LIST	D.LIST or D.TLST

See Appendix IX for data formats.

7. Returning Values

After the proper number of calls on B.PEEL the procedure must put its return value on the stack. This is done by the following code:

MOVE AC, value STACK AC.

If the procedure wishes to return an undefined value, the code would be:

MOVE AC, [D.UNDF] STACK AC.

8. Internal Subroutines

Internal subroutines may be called by CAL subroutine and the subroutine will return with a RET.

9. Saving Accumulators on the Stack

AC's may be saved on the stack by SAVE AC and restored by FETCH AC.

10. Free Storage

To get a block of free storinge N word long, the following code is used: MOVEI TAC, N CAL S.GET

TAC now contains a pointer to the block.

To return a block to free storage, the following code is used:

MOVE TAC, ptr to block CAL S.KETS

APPENDIX IX

DATA FORMATS

All EULER values have special formats.

1. Integer3

The following code converts an EULER integer into a PDP-10 integer:

> LSH AC, 2 ASH AC, -2

The following code converts a PDP-10 integer into an

EULER integer:

. .

. ..

TLO AC, 400000 TLZ AC, 200000

2. Reals

The following code converts an EULER real into a

PDP-10 real:

LSH AC, 1

The following code converts a PDP-10 real into an

EULER real:

LSH AC, -1

3. Booleans

Bit 35=1 is true, and Bit 35=0 is false.

4. Strings

The right half is a pointer to a ASCIZ block of characters.

5. Arrays

The right half is a pointer to an array.

Array format is:

Word 0:	D. INT, ,	number of dimension
Word 1:	D. DOPE , ,	size dimension n
Word n:	D. DOPE , ,	size dimension 1
Word n+1:	value [1,,1,1]	
Word n+2:	value [1,,1,2]	
Word n+ID;	value $[D_1, D_2, \ldots, D_n]$	

6. Lists

The right half is a pointer to a list header: List header

Word -1	D. DUBB	LENGTH	
word 0	N	FIRST ELEMENT PTR	
word 1	Nth ELEMENT PTR	LAST ELEMENT PTR	

List Element

word 0	D.SINB	NEXT	ELEMENT	PTR
word 1	VAL	UE		

62

• • •

• ••

EXTERN JOBHUO, JOB41, JOBREL, JOBDDT, JOBSA, JOBDEN, JOBAPP EXTERN JUBCNI, JOBTPC, JOBOPC S.RET, S.RETS, S.COPY, S. BET, G. HEAD, I.FET, B. PEEL, I. BEET EXTERN WP=1 WOFKING STACK IB=2 :INST. BYTE PTR XP=3 : PUSH-JUMP STACK AR=4 ;ADDP. PEG. LVL=5 BLOCK LEVEL OF LATEST FITCH TI =6 T2:7 T3=16 TAC=11 T4=12 T5=13 T6=14 LP=15 FPEEP1=16 : NOT USED PRESENTLY-NOT PERSISTENT FREEF2=17 ; NOT USED PRESENTLY-NOT PERSISTENT OPDEF FET [POPJ XP.] OPDEF CAL [PUSHJ XP,] OPDEF STACK LPUSH WP.] OPDEF SAVE (PUSH XP.] OPUEF FRITCH [PUP XP.] OPDEF ERE OF [158] DEFINE SKDE (LOC, DESC) < IFE DESC, SKIPGE LOC IFE DESC-IBO, MOVE LOC < SKIPCE TLNE 200000 IFE DESC&3H1-351, MOVE LOC TLZ 774000 IOF [DESC] CAME LOC >> DEFINE SKEN (LOC, DESC) IFE DESC, SKIPL LOC IFE DESC-IEZ, MOVE LOC SKIPGE TLVE 200000 SKIPA IFE DESCK311-3F1. e MOVE LOC TL7. 7748.02 roduced from IOP [DESC] CAMN LOC

64

>> D.FP=0 D. INT=180 D.BOOL=3B1 D.LIST=14186 D.TLST=161B6 D. ARE=14286 D.STH=14386 D. Pk OC=145B6 D.RA=14686 D.REF=14786 D.SDR=151B6 D.BKPT=15086 D. SPA=146B6 D. STDR=15286 D.DOPE=15386 D. SUBR = 15486 D. EXTP=15586 D. PR OP=14486 D. TAR=16286 D. TSTR=16386 D.FSBK=170B6 D.SINB=17136 D.DU63=17286 D.BADE=17386 D.UNDF=17786 . D. UND=17786 TITLE UPROC UP0515, UP1555, UP2555, UP3555, UP4555 INTERN. UP5111, UP6555, UP7111, UP8555, UP9555, UP1555 INTERN UPISSS: RET UPP\$\$\$: UP1555: UP2555: UP35\$1: UP45.5.5 : UP5\$\$5: UP6555: UP7\$15: UP8\$\$\$: UP9\$51: TTCALL 3, [ASCI7./ NO USER PROCEDURES DEFINED 11 CALL [SIXEIT/EXIT/] END

REFERENCES

٠.

1.17

Naur, P. (Ed.) "ALGOL 60: revised report on the algorithmic language". Communications of the ACM, Vol. 6 1-17 (Jan. 1963)

65

Newman, W. M. "An experimental display programming language for the PDP-10 computer". University of Utah, Computer Science Technical Report, UTEC-CSc-70-104 (June, 1970)

Wirth, N. and Weber, H. "Euler: a generalization of Algol and its formal definition". *Communications of the ACM*, Vol. 9 13-25+ and 89-100 (Jan. and Feb., 1966)